

---

# OMSimulator Documentation

*Release v2.0.1*

**Lennart Ochel**

**Feb 08, 2019**



# CONTENTS

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>OMSimulator</b>	<b>3</b>
2.1	OMSimulator Flags . . . . .	3
2.2	Examples . . . . .	4
<b>3</b>	<b>OMSimulatorLib</b>	<b>5</b>
3.1	C-API . . . . .	5
<b>4</b>	<b>OMSimulatorLua</b>	<b>21</b>
4.1	Examples . . . . .	21
4.2	Lua Scripting Commands . . . . .	21
<b>5</b>	<b>OMSimulatorPython</b>	<b>37</b>
5.1	Examples . . . . .	37
5.2	Python Scripting Commands . . . . .	37
<b>6</b>	<b>OMSysIdent</b>	<b>51</b>
6.1	Examples . . . . .	51
6.2	Lua Scripting Commands . . . . .	53
<b>7</b>	<b>SSP Support</b>	<b>57</b>
7.1	Bus Connections . . . . .	57
7.2	TLM Systems . . . . .	58
7.3	TLM Connections . . . . .	59
	<b>Index</b>	<b>67</b>



---

**CHAPTER  
ONE**

---

**INTRODUCTION**

The OMSimulator project is a FMI-based co-simulation tool that supports ordinary (i.e., non-delayed) and TLM connections.



## OMSIMULATOR

OMSimulator is a command line wrapper for the OMSimulatorLib library.

### 2.1 OMSimulator Flags

A brief description of all command line flags will be displayed using OMSimulator --help:

```
info:      Usage: OMSimulator [Options|Lua script]
info:      Options:
          <filename>                      FMU or SSP file
          --clearAllOptions               Reset all flags to default values
          --fetchAllVars=<arg>
          --help [ -h ]                   Displays the help text
          --ignoreInitialUnknowns=<arg>  Ignore the initial unknowns from
→the modelDescrition.xml
          --intervals=<arg> [ -i ]     Specifies the number of
→communication points (arg > 1)
          --logFile=<arg> [ -l ]       Specifies the logfile (stdout is
→used if no log file is specified)
          --logLevel=<arg>              0 default, 1 default+debug, 2
→default+debug+trace
          --mode=<arg> [ -m ]         Forces a certain FMI mode iff the
→FMU provides cs and me [arg: cs (default) or me]
          --progressBar=<arg>
          --resultFile=<arg> [ -r ]    Specifies the name of the output
→result file
          --setInputDerivatives=<arg>
          --solver                       Specifies the integration method
→(internal, euler, cvode)
          --startTime=<arg> [ -s ]     Specifies the start time
          --stopTime=<arg> [ -t ]      Specifies the stop time
          --suppressPath=<arg>
          --tempDir=<arg>              Specifies the temp directory
          --timeout=<arg>              Specifies the maximum allowed time
→in seconds for running a simulation (0 disables)
          --tolerance=<arg>            Specifies the relative tolerance
          --version [ -v ]              Displays version information
          --wallTime=<arg>             Add wall time information for to
→the result file
          --workingDir=<arg>           Specifies the working directory
```

## 2.2 Examples

```
OMSimulator --timeout 180 example.lua
```

## OMSIMULATORLIB

This library is the core of OMSimulator and provides a C interface that can easily be utilized to handle co-simulation scenarios.

### 3.1 C-API

#### 3.1.1 addConnector

Adds a connector to a given component.

```
oms_status_enu_t oms_addConnector(const char* cref, oms_causality_enu_t_
→causality, oms_signal_type_enu_t type);
```

#### 3.1.2 getComponentType

Gets the type of the given component.

```
oms_status_enu_t oms_getComponentType(const char* cref, oms_component_enu_
→t* type);
```

#### 3.1.3 setFixedStepSize

Sets the fixed step size. Can be used for the communication step size of co-simulation systems and also for the integrator step size in model exchange systems.

```
oms_status_enu_t oms_setFixedStepSize(const char* cref, double stepSize);
```

#### 3.1.4 setSolver

Sets the solver method for the given system.

```
oms_status_enu_t oms_setSolver(const char* cref, oms_solver_enu_t solver);
```

### 3.1.5 simulate\_asynchronous

Adds a TLM bus.

```
oms_status_enu_t oms_addTLMBus(const char* cref, oms_tlm_domain_t domain,  
                                const int dimensions, const oms_tlm_interpolation_t interpolation);
```

### 3.1.6 getTLMBus

Gets the TLM bus objects of the given TLM bus cref.

```
oms_status_enu_t oms_getTLMBus(const char* cref, oms_tlmbusconnector_t**  
                                tlmBusConnector);
```

### 3.1.7 setWorkingDirectory

Set a new working directory.

```
oms_status_enu_t oms_setWorkingDirectory(const char* newWorkingDir);
```

### 3.1.8 deleteConnection

Deletes the connection between connectors *crefA* and *crefB*.

```
oms_status_enu_t oms_deleteConnection(const char* crefA, const char*  
                                         crefB);
```

The two arguments *crefA* and *crefB* get swapped automatically if necessary.

### 3.1.9 getSystemType

Gets the type of the given system.

```
oms_status_enu_t oms_getSystemType(const char* cref, oms_system_enu_t*  
                                         type);
```

### 3.1.10 reset

Reset the composite model after a simulation run.

The FMUs go into the same state as after instantiation.

```
oms_status_enu_t oms_reset(const char* cref);
```

### 3.1.11 addSignalsToResults

Add all variables that match the given regex to the result file.

```
oms_status_enu_t oms_addSignalsToResults(const char* cref, const char* regex);
```

The second argument, i.e. regex, is considered as a regular expression (C++11). “.\*” and “(.)\*” can be used to hit all variables.

### 3.1.12 getBus

Gets the bus object.

```
oms_status_enu_t oms_getBus(const char* cref, oms_busconnector_t** busConnector);
```

### 3.1.13 getConnector

Gets the connector object of the given connector cref.

```
oms_status_enu_t oms_getConnector(const char* cref, oms_connector_t** connector);
```

### 3.1.14 listUnconnectedConnectors

Lists all unconnected connectors of a given system.

Memory is allocated for *contents*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
oms_status_enu_t oms_listUnconnectedConnectors(const char* cref, char*** contents);
```

### 3.1.15 getTolerance

Gets the tolerance of a given system or component.

```
oms_status_enu_t oms_getTolerance(const char* cref, double** absoluteTolerance, double* relativeTolerance);
```

### 3.1.16 getBoolean

Get boolean value of given signal.

```
oms_status_enu_t oms_getBoolean(const char* cref, bool* value);
```

### 3.1.17 getElement

Get element information of a given component reference.

```
oms_status_enu_t oms_getElement(const char* cref, oms_element_t** element);
```

### 3.1.18 simulate\_asynchronous

Simulates a composite model in its own thread.

```
oms_status_enu_t oms_simulate_asynchronous(const char* cref, void*
→(*cb)(const char* cref, double time, oms_status_enu_t status));
```

### 3.1.19 deleteConnectorFromTLMBus

Deletes a connector from a given TLM bus.

```
oms_status_enu_t oms_deleteConnectorFromTLMBus(const char* busCref, const
→char* connectorCref);
```

### 3.1.20 setSignalFilter

```
oms_status_enu_t oms_setSignalFilter(const char* cref, const char* regex);
```

### 3.1.21 exportDependencyGraphs

Export the dependency graphs of a given model to dot files.

```
oms_status_enu_t oms_exportDependencyGraphs(const char* cref, const char*
→initialization, const char* simulation);
```

### 3.1.22 getStartTime

Get the start time from the model.

```
oms_status_enu_t oms_getStartTime(const char* cref, double* startTime);
```

### 3.1.23 RunFile

Simulates a single FMU or SSP model.

```
oms_status_enu_t oms_RunFile(const char* filename);
```

### 3.1.24 addConnection

Adds a new connection between connectors *A* and *B*. The connectors need to be specified as fully qualified component references, e.g., “*model.system.component.signal*”.

```
oms_status_enu_t oms_addConnection(const char* crefA, const char* crefB);
```

The two arguments *crefA* and *crefB* get swapped automatically if necessary.

### 3.1.25 copySystem

Copies a system.

```
oms_status_enu_t oms_copySystem(const char* source, const char* target);
```

### 3.1.26 delete

Deletes a connector, component, system, or model object.

```
oms_status_enu_t oms_delete(const char* cref);
```

### 3.1.27 terminate

Terminates a given composite model.

```
oms_status_enu_t oms_terminate(const char* cref);
```

### 3.1.28 setConnectionGeometry

```
oms_status_enu_t oms_setConnectionGeometry(const char* crefA, const char*  
    ↴crefB, const ssd_connection_geometry_t* geometry);
```

### 3.1.29 getModelState

Gets the model state of the given model cref.

```
oms_status_enu_t oms_getModelState(const char* cref, omsModelState_enu_t*  
    ↴modelState);
```

### 3.1.30 getElements

Get list of all sub-components of a given component reference.

```
oms_status_enu_t oms_getElements(const char* cref, oms_element_t***  
    ↴elements);
```

### 3.1.31 setLoggingLevel

Enables/Disables debug logging (logDebug and logTrace).

0 default, 1 default+debug, 2 default+debug+trace

```
void oms_setLoggingLevel(int logLevel);
```

### 3.1.32 getStopTime

Get the stop time from the model.

```
oms_status_enu_t oms_getStopTime(const char* cref, double* stopTime);
```

### 3.1.33 initialize

Initializes a composite model.

```
oms_status_enu_t oms_initialize(const char* cref);
```

### 3.1.34 setBoolean

Set boolean value of given signal.

```
oms_status_enu_t oms_setBoolean(const char* cref, bool value);
```

### 3.1.35 setCommandLineOption

Sets special flags.

```
oms_status_enu_t oms_setCommandLineOption(const char* cmd);
```

Available flags:

```
info:      Usage: OMSimulator [Options|Lua script]
info:      Options:
          <filename>                      FMU or SSP file
          --clearAllOptions               Reset all flags to default values
          --fetchAllVars=<arg>
          --help [ -h ]                   Displays the help text
          --ignoreInitialUnknowns=<arg>   Ignore the initial unknowns from
          ↵the modelDescription.xml
          --intervals=<arg> [ -i ]       Specifies the number of
          ↵communication points (arg > 1)
          --logFile=<arg> [ -l ]         Specifies the logfile (stdout is
          ↵used if no log file is specified)
          --logLevel=<arg>
          ↵default+debug+trace
          --mode=<arg> [ -m ]           Forces a certain FMI mode iff the
          ↵FMU provides cs and me [arg: cs (default) or me]
```

(continues on next page)

(continued from previous page)

```
--progressBar=<arg>
--resultFile=<arg> [ -r ]      Specifies the name of the output_
→result file
    --setInputDerivatives=<arg>
    --solver                      Specifies the integration method_
→(internal, euler, cvode)
    --startTime=<arg> [ -s ]      Specifies the start time
    --stopTime=<arg> [ -t ]       Specifies the stop time
    --suppressPath=<arg>
    --tempDir=<arg>                Specifies the temp directory
    --timeout=<arg>                 Specifies the maximum allowed time_
→in seconds for running a simulation (0 disables)
    --tolerance=<arg>              Specifies the relative tolerance
    --version [ -v ]                Displays version information
    --wallTime=<arg>                Add wall time information for to_
→the result file
    --workingDir=<arg>             Specifies the working directory
```

### 3.1.36 setInteger

Set integer value of given signal.

```
oms_status_enu_t oms_setInteger(const char* cref, int value);
```

### 3.1.37 getReal

Get real value.

```
oms_status_enu_t oms_getReal(const char* cref, double* value);
```

### 3.1.38 addExternalModel

Adds an external model to a TLM system.

```
oms_status_enu_t oms_addExternalModel(const char* cref, const char* path, const char* startscript);
```

### 3.1.39 extractFMIKind

Extracts the FMI kind of a given FMU from the file system.

```
oms_status_enu_t oms_extractFMIKind(const char* filename, oms_fmi_kind_enu_t* kind);
```

### 3.1.40 setElementGeometry

Set geometry information to a given component.

```
oms_status_enu_t oms_setElementGeometry(const char* cref, const ssd_
element_geometry_t* geometry);
```

### 3.1.41 setTLMPositionAndOrientation

Sets initial position and orientation for a TLM 3D interface.

```
oms_status_enu_t oms_setTLMPositionAndOrientation(cref, x1, x2, x3, A11,_
A12, A13, A21, A22, A23, A31, A32, A33);
```

### 3.1.42 getVersion

Returns the library's version string.

```
const char* oms_getVersion();
```

### 3.1.43 cancelSimulation\_asynchronous

Cancels a running asynchronous simulation.

```
oms_status_enu_t oms_cancelSimulation_asynchronous(const char* cref);
```

### 3.1.44 setMaxLogFileSize

Sets maximum log file size in MB. If the file exceeds this limit, the logging will continue on stdout.

```
void oms_setMaxLogFileSize(const unsigned long size);
```

### 3.1.45 simulate

Simulates a composite model.

```
oms_status_enu_t oms_simulate(const char* cref);
```

### 3.1.46 getSubModelPath

Returns the path of a given component.

```
oms_status_enu_t oms_getSubModelPath(const char* cref, char** path);
```

### 3.1.47 addBus

Adds a bus to a given component.

```
oms_status_enu_t oms_addBus(const char* cref);
```

### 3.1.48 setTempDirectory

Set new temp directory.

```
oms_status_enu_t oms_setTempDirectory(const char* newTempDir);
```

### 3.1.49 compareSimulationResults

This function compares a given signal of two result files within absolute and relative tolerances.

```
int oms_compareSimulationResults(const char* filenameA, const char*  
→filenameB, const char* var, double relTol, double absTol);
```

### 3.1.50 rename

Renames a model, system, or component.

```
oms_status_enu_t oms_rename(const char* cref, const char* newCref);
```

### 3.1.51 stepUntil

Simulates a composite model until a given time value.

```
oms_status_enu_t oms_stepUntil(const char* cref, double stopTime);
```

### 3.1.52 parse modelName

Parses the model name from a given SSD representation.

Memory is allocated for *ident*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
oms_status_enu_t oms_parsemodelName(const char* contents, char** cref);
```

### 3.1.53 getTLMVariableTypes

Gets the type of an TLM variable.

```
oms_status_enu_t oms_getTLMVariableTypes(oms_tlm_domain_t domain, const  
→int dimensions, const oms_tlm_interpolation_t interpolation, char  
→***types, char ***descriptions);
```

### 3.1.54 setLoggingInterval

Set the logging interval of the simulation.

```
oms_status_enu_t oms_setLoggingInterval(const char* cref, double  
    ↴loggingInterval);
```

### 3.1.55 setTLMBusGeometry

```
oms_status_enu_t oms_setTLMBusGeometry(const char* bus, const ssd_  
    ↴connector_geometry_t* geometry);
```

### 3.1.56 importString

Imports a composite model from a string.

```
oms_status_enu_t oms_importString(const char* contents, char** cref);
```

### 3.1.57 addSystem

Adds a (sub-)system to a model or system.

```
oms_status_enu_t oms_addSystem(const char* cref, oms_system_enu_t type);
```

### 3.1.58 getConnections

Get list of all connections from a given component.

```
oms_status_enu_t oms_getConnections(const char* cref, oms_connection_t***  
    ↴connections);
```

### 3.1.59 instantiate

Instantiates a given composite model.

```
oms_status_enu_t oms_instantiate(const char* cref);
```

### 3.1.60 freeMemory

Free the memory allocated by some other API. Pass the object for which memory is allocated.

```
void oms_freeMemory(void* obj);
```

### 3.1.61 addTLMConnection

Connects two TLM connectors.

```
oms_status_enu_t oms_addTLMConnection(const char* crefA, const char* crefB,
→ double delay, double alpha, double linearimpedance, double_
→angularimpedance);
```

### 3.1.62 setStartTime

Set the start time of the simulation.

```
oms_status_enu_t oms_setStartTime(const char* cref, double startTime);
```

### 3.1.63 simulate\_realtime

Experimental feature for (soft) real-time simulation.

```
oms_status_enu_t experimental_simulate_realtime(const char* ident);
```

### 3.1.64 export

Exports a composite model to a SPP file.

```
oms_status_enu_t oms_export(const char* cref, const char* filename);
```

### 3.1.65 setStopTime

Set the stop time of the simulation.

```
oms_status_enu_t oms_setStopTime(const char* cref, double stopTime);
```

### 3.1.66 setLoggingCallback

Sets a callback function for the logging system.

```
void oms_setLoggingCallback(void (*cb)(oms_message_type_enu_t type, const_
→char* message));
```

### 3.1.67 getSolver

Gets the selected solver method of the given system.

```
oms_status_enu_t oms_getSolver(const char* cref, oms_solver_enu_t* solver);
```

### 3.1.68 setResultFile

Set the result file of the simulation.

```
oms_status_enu_t oms_setResultFile(const char* cref, const char* filename, int bufferSize);
```

### 3.1.69 getInteger

Get integer value of given signal.

```
oms_status_enu_t oms_getInteger(const char* cref, int* value);
```

### 3.1.70 getVariableStepSize

Gets the step size parameters.

```
oms_status_enu_t oms_getVariableStepSize(const char* cref, double* initialStepSize, double* minimumStepSize, double* maximumStepSize);
```

### 3.1.71 deleteConnectorFromBus

Deletes a connector from a given bus.

```
oms_status_enu_t oms_deleteConnectorFromBus(const char* busCref, const char* connectorCref);
```

### 3.1.72 setTolerance

Sets the tolerance for a given model, system, or component.

```
oms_status_enu_t oms_setTolerance(const char* cref, double absoluteTolerance, double relativeTolerance);
```

### 3.1.73 setVariableStepSize

Sets the step size parameters for methods with stepsize control.

```
oms_status_enu_t oms_getVariableStepSize(const char* cref, double* initialStepSize, double* minimumStepSize, double* maximumStepSize);
```

### 3.1.74 setConnectorGeometry

Set geometry information to a given connector.

```
oms_status_enu_t oms_setConnectorGeometry(const char* cref, const ssd_connector_geometry_t* geometry);
```

### 3.1.75 setTLMConnectionParameters

Simulates a composite model in its own thread.

```
oms_status_enu_t oms_setTLMConnectionParameters(const char* crefA, const char* crefB, const oms_tlm_connection_parameters_t* parameters);
```

### 3.1.76 addConnectorToTLMBus

Adds a connector to a TLM bus.

```
oms_status_enu_t oms_addConnectorToTLMBus(const char* busCref, const char* connectorCref, const char* type);
```

### 3.1.77 setReal

Set real value of given signal.

```
oms_status_enu_t oms_setReal(const char* cref, double value);
```

### 3.1.78 getFixedStepSize

Gets the fixed step size. Can be used for the communication step size of co-simulation systems and also for the integrator step size in model exchange systems.

```
oms_status_enu_t oms_getFixedStepSize(const char* cref, double* stepSize);
```

### 3.1.79 addConnectorToBus

Adds a connector to a bus.

```
oms_status_enu_t oms_addConnectorToBus(const char* busCref, const char* connectorCref);
```

### 3.1.80 setLogFile

Redirects logging output to file or std streams. The warning/error counters are reset.

filename="" to redirect to std streams and proper filename to redirect to file.

```
oms_status_enu_t oms_setLogFile(const char* filename);
```

### 3.1.81 newModel

Creates a new and yet empty composite model.

```
oms_status_enu_t oms_newModel(const char* cref);
```

### 3.1.82 getFMUInfo

Returns FMU specific information.

```
oms_status_enu_t oms_getFMUInfo(const char* cref, const oms_fmu_info_t**  
    ↪fmuInfo);
```

### 3.1.83 importFile

Imports a composite model from a SSP file.

```
oms_status_enu_t oms_importFile(const char* filename, char** cref);
```

### 3.1.84 setActivationRatio

Experimental feature for setting the activation ratio of FMUs for experimenting with multi-rate master algorithms.

```
oms_status_enu_t experimental_setActivationRatio(const char* cref, int k);
```

### 3.1.85 setBusGeometry

```
oms_status_enu_t oms_setBusGeometry(const char* bus, const ssd_connector_  
    ↪geometry_t* geometry);
```

### 3.1.86 list

Lists the SSD representation of a given model, system, or component.

Memory is allocated for *contents*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
oms_status_enu_t oms_list(const char* cref, char** contents);
```

### 3.1.87 setTLMSocketData

Sets data for TLM socket communication.

```
oms_status_enu_t oms_setTLMSocketData(const char* cref, const char*  
    ↪address, int managerPort, int monitorPort);
```

### 3.1.88 removeSignalsFromResults

Removes all variables that match the given regex to the result file.

```
oms_status_enu_t oms_removeSignalsFromResults(const char* cref, const  
→char* regex);
```

The second argument, i.e. regex, is considered as a regular expression (C++11). “.\*” and “(.)\*” can be used to hit all variables.

### 3.1.89 addSubModel

Adds a component to a system.

```
oms_status_enu_t oms_addSubModel(const char* cref, const char* fmuPath);
```



## OMSIMULATORLUA

This is a shared library that provides a Lua interface for the OMSimulatorLib library.

### 4.1 Examples

```
oms_setTempDirectory("./temp/")
oms_newModel("model")
oms_addSystem("model.root", oms_system_sc)

-- instantiate FMUs
oms_addSubModel("model.root.system1", "FMUs/System1.fmu")
oms_addSubModel("model.root.system2", "FMUs/System2.fmu")

-- add connections
oms_addConnection("model.root.system1.y", "model.root.system2.u")
oms_addConnection("model.root.system2.y", "model.root.system1.u")

-- simulation settings
oms setResultFile("model", "results.mat")
oms_setStopTime("model", 0.1)
oms_setFixedStepSize("model.root", 1e-4)

oms_instantiate("model")
oms_setReal("model.root.system1.x_start", 2.5)

oms_initialize("model")
oms_simulate("model")
oms_terminate("model")
oms_delete("model")
```

### 4.2 Lua Scripting Commands

#### 4.2.1 addConnector

Adds a connector to a given component.

```
status = oms_addConnector(cref, causality, type)
```

#### 4.2.2 getComponentType

Gets the type of the given component.

```
# not available
```

#### 4.2.3 setFixedStepSize

Sets the fixed step size. Can be used for the communication step size of co-simulation systems and also for the integrator step size in model exchange systems.

```
status = oms_setFixedStepSize(cref, stepSize)
```

#### 4.2.4 setSolver

Sets the solver method for the given system.

```
status = oms_setSolver(cref, solver)
```

solver	Type	Description
oms_solver_sc_explicit_euler	sc-system	Explicit euler with fixed step size
oms_solver_sc_cvode	sc-system	CVODE with adaptive stepsize
oms_solver_wc_ma	wc-system	default master algorithm with fixed step size
oms_solver_wc_mav	wc-system	master algorithm with adaptive stepsize

#### 4.2.5 simulate\_asynchronous

Adds a TLM bus.

```
status = oms_addTLMBus(cref, domain, dimensions, interpolation)
```

#### 4.2.6 getTLMBus

Gets the TLM bus objects of the given TLM bus cref.

```
# not available
```

#### 4.2.7 setWorkingDirectory

Set a new working directory.

```
status = oms_setWorkingDirectory(newWorkingDir)
```

#### 4.2.8 deleteConnection

Deletes the connection between connectors *crefA* and *crefB*.

```
status = oms_deleteConnection(crefA, crefB)
```

The two arguments *crefA* and *crefB* get swapped automatically if necessary.

#### 4.2.9 getSystemType

Gets the type of the given system.

```
# not available
```

#### 4.2.10 reset

Reset the composite model after a simulation run.

The FMUs go into the same state as after instantiation.

```
status = oms_reset(cref)
```

#### 4.2.11 addSignalsToResults

Add all variables that match the given regex to the result file.

```
status = oms_addSignalsToResults(cref, regex)
```

The second argument, i.e. *regex*, is considered as a regular expression (C++11). “.\*” and “(.)\*” can be used to hit all variables.

#### 4.2.12 getBus

Gets the bus object.

```
# not available
```

#### 4.2.13 getConnector

Gets the connector object of the given connector cref.

```
# not available
```

#### 4.2.14 listUnconnectedConnectors

Lists all unconnected connectors of a given system.

Memory is allocated for *contents*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
contents, status = oms_listUnconnectedConnectors(cref)
```

#### **4.2.15 getTolerance**

Gets the tolerance of a given system or component.

```
absoluteTolerance, relativeTolerance, status = oms_getTolerance(cref)
```

#### **4.2.16 getBoolean**

Get boolean value of given signal.

```
value, status = oms_getBoolean(cref)
```

#### **4.2.17 getElement**

Get element information of a given component reference.

```
# not available
```

#### **4.2.18 simulate\_asynchronous**

Simulates a composite model in its own thread.

```
# not available
```

#### **4.2.19 deleteConnectorFromTLMBus**

Deletes a connector from a given TLM bus.

```
status = oms_deleteConnectorFromTLMBus(busCref, connectorCref)
```

#### **4.2.20 setSignalFilter**

```
status = oms_setSignalFilter(cref, regex)
```

#### **4.2.21 exportDependencyGraphs**

Export the dependency graphs of a given model to dot files.

```
status = oms_exportDependencyGraphs(cref, initialization, simulation)
```

## 4.2.22 getStartTime

Get the start time from the model.

```
startTime, status = oms_getStartTime(cref)
```

## 4.2.23 RunFile

Simulates a single FMU or SSP model.

```
# not available
```

## 4.2.24 addConnection

Adds a new connection between connectors *A* and *B*. The connectors need to be specified as fully qualified component references, e.g., “*model.system.component.signal*”.

```
status = oms_addConnection(crefA, crefB)
```

The two arguments *crefA* and *crefB* get swapped automatically if necessary.

## 4.2.25 copySystem

Copies a system.

```
status = oms_copySystem(source, target)
```

## 4.2.26 delete

Deletes a connector, component, system, or model object.

```
status = oms_delete(cref)
```

## 4.2.27 terminate

Terminates a given composite model.

```
status = oms_terminate(cref)
```

## 4.2.28 setConnectionGeometry

```
# not available
```

#### 4.2.29 getModelState

Gets the model state of the given model cref.

```
# not available
```

#### 4.2.30 getElements

Get list of all sub-components of a given component reference.

```
# not available
```

#### 4.2.31 setLoggingLevel

Enables/Disables debug logging (logDebug and logTrace).

0 default, 1 default+debug, 2 default+debug+trace

```
oms_setLoggingLevel(logLevel)
```

#### 4.2.32 getStopTime

Get the stop time from the model.

```
stopTime, status = oms_getStopTime(cref)
```

#### 4.2.33 initialize

Initializes a composite model.

```
status = oms_initialize(cref)
```

#### 4.2.34 setBoolean

Set boolean value of given signal.

```
status = oms_setBoolean(cref, value)
```

#### 4.2.35 setCommandLineOption

Sets special flags.

```
status = oms_setCommandLineOption(cmd)
```

Available flags:

```

info:    Usage: OMSimulator [Options|Lua script]
info:    Options:
          <filename>           FMU or SSP file
          --clearAllOptions   Reset all flags to default values
          --fetchAllVars=<arg>
          --help [ -h ]         Displays the help text
          --ignoreInitialUnknowns=<arg> Ignore the initial unknowns from
→the modelDesction.xml
          --intervals=<arg> [ -i ]      Specifies the number of
→communication points (arg > 1)
          --logFile=<arg> [ -l ]      Specifies the logfile (stdout is
→used if no log file is specified)
          --logLevel=<arg>
→default+debug+trace
          --mode=<arg> [ -m ]        Forces a certain FMI mode iff the
→FMU provides cs and me [arg: cs (default) or me]
          --progressBar=<arg>
          --resultFile=<arg> [ -r ]      Specifies the name of the output
→result file
          --setInputDerivatives=<arg>
          --solver               Specifies the integration method
→(internal, euler, cvode)
          --startTime=<arg> [ -s ]      Specifies the start time
          --stopTime=<arg> [ -t ]       Specifies the stop time
          --suppressPath=<arg>
          --tempDir=<arg>             Specifies the temp directory
          --timeout=<arg>              Specifies the maximum allowed time
→in seconds for running a simulation (0 disables)
          --tolerance=<arg>            Specifies the relative tolerance
          --version [ -v ]             Displays version information
          --wallTime=<arg>              Add wall time information for to
→the result file
          --workingDir=<arg>           Specifies the working directory

```

#### 4.2.36 setInteger

Set integer value of given signal.

```
status = oms_setInteger(cref, value)
```

#### 4.2.37 getReal

Get real value.

```
value, status = oms_getReal(cref)
```

#### 4.2.38 addExternalModel

Adds an external model to a TLM system.

```
status = oms_addExternalModel(cref, path, startscript)
```

#### 4.2.39 extractFMIKind

Extracts the FMI kind of a given FMU from the file system.

```
# not available
```

#### 4.2.40 setElementGeometry

Set geometry information to a given component.

```
# not available
```

#### 4.2.41 setTLMPositionAndOrientation

Sets initial position and orientation for a TLM 3D interface.

```
status oms_setTLMPositionAndOrientation(cref, x1, x2, x3, A11, A12, A13,  
                                     ↪A21, A22, A23, A31, A32, A33)
```

#### 4.2.42 getVersion

Returns the library's version string.

```
version = oms_getVersion()
```

#### 4.2.43 cancelSimulation\_asynchronous

Cancels a running asynchronous simulation.

```
# not available
```

#### 4.2.44 setMaxLogFileSize

Sets maximum log file size in MB. If the file exceeds this limit, the logging will continue on stdout.

```
oms_setMaxLogFileSize(size)
```

#### 4.2.45 simulate

Simulates a composite model.

```
status = oms_simulate(cref)
```

#### 4.2.46 getSubModelPath

Returns the path of a given component.

```
# not available
```

#### 4.2.47 addBus

Adds a bus to a given component.

```
status = oms_addBus (cref)
```

#### 4.2.48 setTempDirectory

Set new temp directory.

```
status = oms_setTempDirectory (newTempDir)
```

#### 4.2.49 compareSimulationResults

This function compares a given signal of two result files within absolute and relative tolerances.

```
oms_compareSimulationResults (filenameA, filenameB, var, relTol, absTol)
```

The following table describes the input values:

Input	Type	Description
filenameA	String	Name of first result file to compare.
filenameB	String	Name of second result file to compare.
var	String	Name of signal to compare.
relTol	Number	Relative tolerance.
absTol	Number	Absolute tolerance.

The following table describes the return values:

Type	Description
Integer	1 if the signal is considered as equal, 0 otherwise

#### 4.2.50 rename

Renames a model, system, or component.

```
status = oms_rename (cref, newCref)
```

#### 4.2.51 stepUntil

Simulates a composite model until a given time value.

```
status = oms_stepUntil(cref, stopTime)
```

#### 4.2.52 parse modelName

Parses the model name from a given SSD representation.

Memory is allocated for *ident*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
ident, status = oms_parsemodelName(contents)
```

#### 4.2.53 getTLMVariableTypes

Gets the type of an TLM variable.

```
# not available
```

#### 4.2.54 setLoggingInterval

Set the logging interval of the simulation.

```
status = oms_setLoggingInterval(cref, loggingInterval)
```

#### 4.2.55 setTLMBusGeometry

```
# not available
```

#### 4.2.56 importString

Imports a composite model from a string.

```
cref, oms_status_enu_t oms_importString(contents)
```

#### 4.2.57 addSystem

Adds a (sub-)system to a model or system.

```
status = oms_addSystem(cref, type)
```

#### 4.2.58 getConnections

Get list of all connections from a given component.

```
# not available
```

#### 4.2.59 instantiate

Instantiates a given composite model.

```
status = oms_instantiate(cref)
```

#### 4.2.60 freeMemory

Free the memory allocated by some other API. Pass the object for which memory is allocated.

```
oms_freeMemory(obj)
```

#### 4.2.61 addTLMConnection

Connects two TLM connectors.

```
status = oms_addTLMConnection(crefA, crefB, delay, alpha, linearimpedance,  
    ↴angularimpedance)
```

#### 4.2.62 setStartTime

Set the start time of the simulation.

```
status = oms_setStartTime(cref, startTime)
```

#### 4.2.63 simulate\_realtime

Experimental feature for (soft) real-time simulation.

```
status = experimental_simulate_realtime(ident)
```

#### 4.2.64 export

Exports a composite model to a SPP file.

```
status = oms_export(cref, filename)
```

#### 4.2.65 setStopTime

Set the stop time of the simulation.

```
status = oms_setStopTime(cref, stopTime)
```

#### 4.2.66 setLoggingCallback

Sets a callback function for the logging system.

```
# not available
```

#### 4.2.67 getSolver

Gets the selected solver method of the given system.

```
solver, status = oms_getSolver(cref)
```

#### 4.2.68 setResultFile

Set the result file of the simulation.

```
status = oms_setResultFile(cref, filename)
status = oms_setResultFile(cref, filename, bufferSize)
```

#### 4.2.69 getInteger

Get integer value of given signal.

```
value, status = oms_getInteger(cref)
```

#### 4.2.70 getVariableStepSize

Gets the step size parameters.

```
initialStepSize, minimumStepSize, maximumStepSize, status = oms_
→getVariableStepSize(cref)
```

#### 4.2.71 deleteConnectorFromBus

Deletes a connector from a given bus.

```
status = oms_deleteConnectorFromBus(busCref, connectorCref)
```

#### 4.2.72 setTolerance

Sets the tolerance for a given model, system, or component.

```
status = oms_setTolerance(const char* cref, double tolerance)
status = oms_setTolerance(const char* cref, double absoluteTolerance, ↴
    double relativeTolerance)
```

#### 4.2.73 setVariableStepSize

Sets the step size parameters for methods with stepsize control.

```
status = oms_getVariableStepSize(cref, initialStepSize, minimumStepSize, ↴
    maximumStepSize)
```

#### 4.2.74 setConnectorGeometry

Set geometry information to a given connector.

```
# not available
```

#### 4.2.75 setTLMConnectionParameters

Simulates a composite model in its own thread.

```
# not available
```

#### 4.2.76 addConnectorToTLMBus

Adds a connector to a TLM bus.

```
status = oms_addConnectorToTLMBus(busCref, connectorCref, type)
```

#### 4.2.77 setReal

Set real value of given signal.

```
status = oms_setReal(cref, value)
```

#### 4.2.78 getFixedStepSize

Gets the fixed step size. Can be used for the communication step size of co-simulation systems and also for the integrator step size in model exchange systems.

```
stepSize, status = oms_setFixedStepSize(cref)
```

#### 4.2.79 addConnectorToBus

Adds a connector to a bus.

```
status = oms_addConnectorToBus (busCref, connectorCref)
```

#### 4.2.80 setLogFile

Redirects logging output to file or std streams. The warning/error counters are reset.

filename="" to redirect to std streams and proper filename to redirect to file.

```
status = oms_setLogFile (filename)
```

#### 4.2.81 newModel

Creates a new and yet empty composite model.

```
status = oms_newModel (cref)
```

#### 4.2.82 getFMUInfo

Returns FMU specific information.

```
# not available
```

#### 4.2.83 importFile

Imports a composite model from a SSP file.

```
cref, status = oms_importFile (filename)
```

#### 4.2.84 setActivationRatio

Experimental feature for setting the activation ratio of FMUs for experimenting with multi-rate master algorithms.

```
status = experimental_setActivationRatio (cref, k)
```

#### 4.2.85 setBusGeometry

```
# not available
```

#### 4.2.86 list

Lists the SSD representation of a given model, system, or component.

Memory is allocated for *contents*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
contents, status = oms_list(cref)
```

#### 4.2.87 setTLMSocketData

Sets data for TLM socket communication.

```
status = oms_setTLMSocketData(cref, address, managerPort, monitorPort)
```

#### 4.2.88 removeSignalsFromResults

Removes all variables that match the given regex to the result file.

```
status = oms_removeSignalsFromResults(cref, regex)
```

The second argument, i.e. *regex*, is considered as a regular expression (C++11). “.\*” and “(.)\*” can be used to hit all variables.

#### 4.2.89 addSubModel

Adds a component to a system.

```
status = oms_addSubModel(cref, fmuPath)
```



## OMSIMULATORPYTHON

This is a shared library that provides a Python interface for the OMSimulatorLib library.

### 5.1 Examples

```
from OMSimulator import OMSimulator
oms.setTempDirectory("./temp/")
oms.newModel("model")
oms.addSystem("model.root", oms.system_sc)

# instantiate FMUs
oms.addSubModel("model.root.system1", "FMUs/System1.fmu")
oms.addSubModel("model.root.system2", "FMUs/System2.fmu")

# add connections
oms.addConnection("model.root.system1.y", "model.root.system2.u")
oms.addConnection("model.root.system2.y", "model.root.system1.u")

# simulation settings
oms.setResultFile("model", "results.mat")
oms.setStopTime("model", 0.1)
oms.setFixedStepSize("model.root", 1e-4)

oms.instantiate("model")
oms.setReal("model.root.system1.x_start", 2.5)

oms.initialize("model")
oms.simulate("model")
oms.terminate("model")
oms.delete("model")
```

### 5.2 Python Scripting Commands

#### 5.2.1 addConnector

Adds a connector to a given component.

```
status = oms.addConnector(cref, causality, type)
```

## 5.2.2 getComponentType

Gets the type of the given component.

```
# not available
```

## 5.2.3 setFixedStepSize

Sets the fixed step size. Can be used for the communication step size of co-simulation systems and also for the integrator step size in model exchange systems.

```
status = oms.setFixedStepSize(cref, stepSize)
```

## 5.2.4 setSolver

Sets the solver method for the given system.

```
status = oms.setSolver(cref, solver)
```

## 5.2.5 simulate\_asynchronous

Adds a TLM bus.

```
status = oms.addTLMBus(cref, domain, dimensions, interpolation)
```

## 5.2.6 getTLMBus

Gets the TLM bus objects of the given TLM bus cref.

```
# not available
```

## 5.2.7 setWorkingDirectory

Set a new working directory.

```
status = oms.setWorkingDirectory(newWorkingDir)
```

## 5.2.8 deleteConnection

Deletes the connection between connectors *crefA* and *crefB*.

```
status = oms.deleteConnection(crefA, crefB)
```

The two arguments *crefA* and *crefB* get swapped automatically if necessary.

### 5.2.9 getSystemType

Gets the type of the given system.

```
# not available
```

### 5.2.10 reset

Reset the composite model after a simulation run.

The FMUs go into the same state as after instantiation.

```
status = oms.reset(cref)
```

### 5.2.11 addSignalsToResults

Add all variables that match the given regex to the result file.

```
status = oms.addSignalsToResults(cref, regex)
```

The second argument, i.e. regex, is considered as a regular expression (C++11). “.\*” and “(.)\*” can be used to hit all variables.

### 5.2.12 getBus

Gets the bus object.

```
# not available
```

### 5.2.13 getConnector

Gets the connector object of the given connector cref.

```
# not available
```

### 5.2.14 listUnconnectedConnectors

Lists all unconnected connectors of a given system.

Memory is allocated for *contents*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
contents, status = oms.listUnconnectedConnectors(cref)
```

### **5.2.15 getTolerance**

Gets the tolerance of a given system or component.

```
absoluteTolerance, relativeTolerance, status = oms.getTolerance(cref)
```

### **5.2.16 getBoolean**

Get boolean value of given signal.

```
value, status = oms.getBoolean(cref)
```

### **5.2.17 getElement**

Get element information of a given component reference.

```
# not available
```

### **5.2.18 simulate\_asynchronous**

Simulates a composite model in its own thread.

```
# not available
```

### **5.2.19 deleteConnectorFromTLMBus**

Deletes a connector from a given TLM bus.

```
status = oms.deleteConnectorFromTLMBus(busCref, connectorCref)
```

### **5.2.20 setSignalFilter**

```
status = oms.setSignalFilter(cref, regex)
```

### **5.2.21 exportDependencyGraphs**

Export the dependency graphs of a given model to dot files.

```
status = oms.exportDependencyGraphs(cref, initialization, simulation)
```

### **5.2.22 getStartTime**

Get the start time from the model.

```
startTime, status = oms.getStartTime(cref)
```

### 5.2.23 RunFile

Simulates a single FMU or SSP model.

```
# not available
```

### 5.2.24 addConnection

Adds a new connection between connectors *A* and *B*. The connectors need to be specified as fully qualified component references, e.g., “*model.system.component.signal*”.

```
status = oms.addConnection(crefA, crefB)
```

The two arguments *crefA* and *crefB* get swapped automatically if necessary.

### 5.2.25 copySystem

Copies a system.

```
status = oms.copySystem(source, target)
```

### 5.2.26 delete

Deletes a connector, component, system, or model object.

```
status = oms.delete(cref)
```

### 5.2.27 terminate

Terminates a given composite model.

```
status = oms.terminate(cref)
```

### 5.2.28 setConnectionGeometry

```
# not available
```

### 5.2.29 getModelState

Gets the model state of the given model cref.

```
# not available
```

### **5.2.30 getElements**

Get list of all sub-components of a given component reference.

```
# not available
```

### **5.2.31 setLoggingLevel**

Enables/Disables debug logging (logDebug and logTrace).

0 default, 1 default+debug, 2 default+debug+trace

```
oms.setLoggingLevel(logLevel)
```

### **5.2.32 getStopTime**

Get the stop time from the model.

```
stopTime, status = oms.getStopTime(cref)
```

### **5.2.33 initialize**

Initializes a composite model.

```
status = oms.initialize(cref)
```

### **5.2.34 setBoolean**

Set boolean value of given signal.

```
status = oms.setBoolean(cref, value)
```

### **5.2.35 setCommandLineOption**

Sets special flags.

```
status = oms.setCommandLineOption(cmd)
```

Available flags:

```
info:      Usage: OMSimulator [Options|Lua script]
info:      Options:
          <filename>                                FMU or SSP file
          --clearAllOptions                         Reset all flags to default values
          --fetchAllVars=<arg>
          --help [ -h ]                               Displays the help text
          --ignoreInitialUnknowns=<arg>   Ignore the initial unknowns from
          ↪the modelDesction.xml
          --intervals=<arg> [ -i ]     Specifies the number of
          ↪communication points (arg > 1)           (continues on next page)
```

(continued from previous page)

--logFile=<arg> [ -l ]	Specifies the logfile (stdout is <u>0</u> default, <u>1</u> default+debug, <u>2</u>
↳ used <b>if</b> no log file is specified)	
--logLevel=<arg>	<u>0</u> default, <u>1</u> default+debug, <u>2</u>
↳ default+debug+trace	
--mode=<arg> [ -m ]	Forces a certain FMI mode iff the <u>FMU</u> provides cs and me [arg: cs (default) or me]
--progressBar=<arg>	
--resultFile=<arg> [ -r ]	Specifies the name of the output <u>result</u> file
↳ result file	
--setInputDerivatives=<arg>	
--solver	Specifies the integration method <u>internal</u>
↳ (internal, euler, cvode)	
--startTime=<arg> [ -s ]	Specifies the start time
--stopTime=<arg> [ -t ]	Specifies the stop time
--suppressPath=<arg>	
--tempDir=<arg>	Specifies the temp directory
--timeout=<arg>	Specifies the maximum allowed <u>time</u> (0 disables)
↳ in seconds <b>for</b> running a simulation	
--tolerance=<arg>	Specifies the relative tolerance
--version [ -v ]	Displays version information
--wallTime=<arg>	Add wall <u>time</u> information <b>for</b> to <u>the result</u> file
↳ the result file	
--workingDir=<arg>	Specifies the working directory

### 5.2.36 setInteger

Set integer value of given signal.

```
status = oms.setInteger(cref, value)
```

### 5.2.37 getReal

Get real value.

```
value, status = oms.getReal(cref)
```

### 5.2.38 addExternalModel

Adds an external model to a TLM system.

```
status = oms.addExternalModel(cref, path, startscript)
```

### 5.2.39 extractFMIKind

Extracts the FMI kind of a given FMU from the file system.

```
# not available
```

## 5.2.40 setElementGeometry

Set geometry information to a given component.

```
# not available
```

## 5.2.41 setTLMPositionAndOrientation

Sets initial position and orientation for a TLM 3D interface.

```
# not yet available
```

## 5.2.42 getVersion

Returns the library's version string.

```
oms = OMSimulator()  
oms.getVersion()
```

## 5.2.43 cancelSimulation\_asynchronous

Cancels a running asynchronous simulation.

```
# not available
```

## 5.2.44 setMaxLogFileSize

Sets maximum log file size in MB. If the file exceeds this limit, the logging will continue on stdout.

```
oms.setMaxLogFileSize(size)
```

## 5.2.45 simulate

Simulates a composite model.

```
status = oms.simulate(cref)
```

## 5.2.46 getSubModelPath

Returns the path of a given component.

```
path, status = oms.getSubModelPath(cref)
```

### 5.2.47 addBus

Adds a bus to a given component.

```
status = oms.addBus(cref)
```

### 5.2.48 setTempDirectory

Set new temp directory.

```
status = oms.setTempDirectory(newTempDir)
```

### 5.2.49 compareSimulationResults

This function compares a given signal of two result files within absolute and relative tolerances.

```
oms.compareSimulationResults(filenameA, filenameB, var, relTol, absTol)
```

### 5.2.50 rename

Renames a model, system, or component.

```
status = oms.rename(cref, newCref)
```

### 5.2.51 stepUntil

Simulates a composite model until a given time value.

```
status = oms.stepUntil(cref, stopTime)
```

### 5.2.52 parse modelName

Parses the model name from a given SSD representation.

Memory is allocated for *ident*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
ident, status = oms.parsemodelName(contents)
```

### 5.2.53 getTLMVariableTypes

Gets the type of an TLM variable.

```
# not available
```

### 5.2.54 setLoggingInterval

Set the logging interval of the simulation.

```
status = oms.setLoggingInterval(cref, loggingInterval)
```

### 5.2.55 setTLMBusGeometry

```
# not available
```

### 5.2.56 importString

Imports a composite model from a string.

```
cref, oms_status_enu_t oms.importString(contents)
```

### 5.2.57 addSystem

Adds a (sub-)system to a model or system.

```
status = oms.addSystem(cref, type)
```

### 5.2.58 getConnections

Get list of all connections from a given component.

```
# not available
```

### 5.2.59 instantiate

Instantiates a given composite model.

```
status = oms.instantiate(cref)
```

### 5.2.60 freeMemory

Free the memory allocated by some other API. Pass the object for which memory is allocated.

```
oms.freeMemory(obj)
```

### 5.2.61 addTLMConnection

Connects two TLM connectors.

```
status = oms.addTLMConnection(crefA, crefB, delay, alpha, linearimpedance,
                               ↴angularimpedance)
```

## 5.2.62 setStartTime

Set the start time of the simulation.

```
status = oms.setStartTime(cref, startTime)
```

## 5.2.63 simulate\_realtime

Experimental feature for (soft) real-time simulation.

```
# not yet available
```

## 5.2.64 export

Exports a composite model to a SPP file.

```
status = oms.export(cref, filename)
```

## 5.2.65 setStopTime

Set the stop time of the simulation.

```
status = oms.setStopTime(cref, stopTime)
```

## 5.2.66 setLoggingCallback

Sets a callback function for the logging system.

```
# not available
```

## 5.2.67 getSolver

Gets the selected solver method of the given system.

```
solver, status = oms.getSolver(cref)
```

## 5.2.68 setResultFile

Set the result file of the simulation.

```
status = oms.setResultFile(cref, filename)
status = oms.setResultFile(cref, filename, bufferSize)
```

## 5.2.69 getInteger

Get integer value of given signal.

```
value, status = oms.getInteger(cref)
```

## 5.2.70 getVariableStepSize

Gets the step size parameters.

```
initialStepSize, minimumStepSize, maximumStepSize, status = oms.  
    ↪getVariableStepSize(cref)
```

## 5.2.71 deleteConnectorFromBus

Deletes a connector from a given bus.

```
status = oms.deleteConnectorFromBus(busCref, connectorCref)
```

## 5.2.72 setTolerance

Sets the tolerance for a given model, system, or component.

```
status = oms.setTolerance(const char* cref, double tolerance)  
status = oms.setTolerance(const char* cref, double absoluteTolerance, ↴  
    ↪double relativeTolerance)
```

## 5.2.73 setVariableStepSize

Sets the step size parameters for methods with stepsize control.

```
status = oms.getVariableStepSize(cref, initialStepSize, minimumStepSize, ↴  
    ↪maximumStepSize)
```

## 5.2.74 setConnectorGeometry

Set geometry information to a given connector.

```
# not available
```

## 5.2.75 setTLMConnectionParameters

Simulates a composite model in its own thread.

```
# not available
```

### 5.2.76 addConnectorToTLMBus

Adds a connector to a TLM bus.

```
status = oms.addConnectorToTLMBus(busCref, connectorCref, type)
```

### 5.2.77 setReal

Set real value of given signal.

```
status = oms.setReal(cref, value)
```

### 5.2.78 getFixedStepSize

Gets the fixed step size. Can be used for the communication step size of co-simulation systems and also for the integrator step size in model exchange systems.

```
stepSize, status = oms.getFixedStepSize(cref)
```

### 5.2.79 addConnectorToBus

Adds a connector to a bus.

```
status = oms.addConnectorToBus(busCref, connectorCref)
```

### 5.2.80 setLogFile

Redirects logging output to file or std streams. The warning/error counters are reset.

filename="" to redirect to std streams and proper filename to redirect to file.

```
status = oms.setLogFile(filename)
```

### 5.2.81 newModel

Creates a new and yet empty composite model.

```
status = oms.newModel(cref)
```

### 5.2.82 getFMUInfo

Returns FMU specific information.

```
# not available
```

### 5.2.83 importFile

Imports a composite model from a SSP file.

```
cref, status = oms.importFile(filename)
```

### 5.2.84 setActivationRatio

Experimental feature for setting the activation ratio of FMUs for experimenting with multi-rate master algorithms.

```
# not yet available
```

### 5.2.85 setBusGeometry

```
# not available
```

### 5.2.86 list

Lists the SSD representation of a given model, system, or component.

Memory is allocated for *contents*. The caller is responsible to free it using the C-API. The Lua and Python bindings take care of the memory and the caller doesn't need to call free.

```
contents, status = oms.list(cref)
```

### 5.2.87 setTLMSocketData

Sets data for TLM socket communication.

```
# not yet available
```

### 5.2.88 removeSignalsFromResults

Removes all variables that match the given regex to the result file.

```
status = oms.removeSignalsFromResults(cref, regex)
```

The second argument, i.e. regex, is considered as a regular expression (C++11). “.\*” and “(.)\*” can be used to hit all variables.

### 5.2.89 addSubModel

Adds a component to a system.

```
status = oms.addSubModel(cref, fmuPath)
```

## OMSYSIDENT

OMSysIdent is a module for the parameter estimation of behavioral models (wrapped as FMUs) on top of the OMSimulator API. It uses the Ceres solver (<http://ceres-solver.org/>) for the optimization task.

It is an optional module which can be disabled. Please check the build files for your platform for the respective flags.

### 6.1 Examples

There are examples in the testsuite below the subfolder *OMSysIdent* which use the scripting API. In addition there are examples which directly use the C API within the module's source code folder (*src/OMSysIdentLib*).

Below is a basic example from the testsuite (*HelloWorld\_cs\_Fit.lua*) which uses the Lua scripting API. It determines the parameters for the following “hello world” style Modelica model:

```
model HelloWorld
  parameter Real a = -1;
  parameter Real x_start = 1;
  Real x(start=x_start, fixed=true);
equation
  der(x) = a*x;
end HelloWorld;
```

The goal is to estimate the value of the coefficient *a* and the initial value *x\_start* of the state variable *x*. Instead of real measurements, the script simply uses simulation data generated from the *HelloWorld* examples as measurement data. The array *data\_time* contains the time instants at which a sample is taken and the array *data\_x* contains the value of *x* that corresponds to the respective time instant.

The estimation parameters are defined by calls to function *oms\_i\_addParameter(..)* in which the name of the parameter and a first guess for the parameter's value is stated.

Listing 1: *HelloWorld\_cs\_Fit.lua*

```
oms_setTempDirectory("./HelloWorld_cs_Fit/")
oms_newModel("HelloWorld_cs_Fit")
oms_addSystem("HelloWorld_cs_Fit.root", oms_system_wc)

-- add FMU
oms_addSubModel("HelloWorld_cs_Fit.root.HelloWorld", ".../FMUs/HelloWorld.
↪fmu")
```

(continues on next page)

(continued from previous page)

```
-- create system identification model for model
simodel = omsi_newSysIdentModel("HelloWorld_cs_Fit");

-- Data generated from simulating HelloWorld.mo for 1.0s with Euler and 0.
-- step size
kNumSeries = 1;
kNumObservations = 11;
data_time = {0.0, 0.1, 0.2, 0.3, 0.4, 0.5, 0.6, 0.7, 0.8, 0.9, 1};
inputvars = {};
measurementvars = {"HelloWorld_cs_Fit.root.HelloWorld.x"};
data_x = {1, 0.9, 0.8100000000000001, 0.7290000000000001, 0.6561, 0.
--5904900000000001, 0.5314410000000001, 0.4782969000000001, 0.43046721, 0.
--387420489, 0.3486784401};

omsi_initialize(simodel, kNumSeries, data_time, inputvars, measurementvars)
-- omsi_describe(simodel)

omsi_addParameter(simodel, "HelloWorld_cs_Fit.root.HelloWorld.x_start", 0.
--5);
omsi_addParameter(simodel, "HelloWorld_cs_Fit.root.HelloWorld.a", -0.5);
omsi_addMeasurement(simodel, 0, "HelloWorld_cs_Fit.root.HelloWorld.x",_
--data_x);
-- omsi_describe(simodel)

omsi_setOptions_max_num_iterations(simodel, 25)
omsi_solve(simodel, "BriefReport")

status, simodelstate = omsi_getState(simodel);
-- print(status, simodelstate)

status, startvalue1, estimatedvalue1 = omsi_getParameter(simodel,
--"HelloWorld_cs_Fit.root.HelloWorld.a")
status, startvalue2, estimatedvalue2 = omsi_getParameter(simodel,
--"HelloWorld_cs_Fit.root.HelloWorld.x_start")
-- print("HelloWorld.a startvalue=" .. startvalue1 .. ", estimatedvalue=" ..
--estimatedvalue1)
-- print("HelloWorld.x_start startvalue=" .. startvalue2 .. ", "
--estimatedvalue=" .. estimatedvalue2)
is_OK1 = estimatedvalue1 > -1.1 and estimatedvalue1 < -0.9
is_OK2 = estimatedvalue2 > 0.9 and estimatedvalue2 < 1.1
print("HelloWorld.a estimation is OK: " .. tostring(is_OK1))
print("HelloWorld.x_start estimation is OK: " .. tostring(is_OK2))

omsi_freeSysIdentModel(simodel)

oms_terminate("HelloWorld_cs_Fit")
oms_delete("HelloWorld_cs_Fit")
```

Running the script generates the following console output:

iter	cost	cost_change	gradient	step	tr_ratio	tr_
radius	ls_iter	iter_time	total_time			
0	4.034320e-01	0.00e+00	2.19e+00	0.00e+00	0.00e+00	1.00e+04
1	3.821520e-02	3.65e-01	4.11e-01	9.87e-01	9.06e-01	2.15e+04

(continues on next page)

(continued from previous page)

```

2 6.837776e-04   3.75e-02   5.19e-02   3.58e-01   9.83e-01   6.46e+04   ↵
↪ 1   2.77e-02   8.02e-02
3 1.354499e-07   6.84e-04   6.08e-04   4.58e-02   1.00e+00   1.94e+05   ↵
↪ 1   2.96e-02   1.10e-01
4 5.854620e-15   1.35e-07   1.09e-07   7.22e-04   1.00e+00   5.82e+05   ↵
↪ 1   3.08e-02   1.41e-01
5 1.160287e-25   5.85e-15   2.26e-13   1.59e-07   1.00e+00   1.74e+06   ↵
↪ 1   2.86e-02   1.69e-01
Ceres Solver Report: Iterations: 6, Initial cost: 4.034320e-01, Final ↵
↪ cost: 1.160287e-25, Termination: CONVERGENCE

=====
Total duration for parameter estimation: 169msec.
Result of parameter estimation (check 'Termination' status above whether ↵
↪solver converged):

HelloWorld_cs_Fit.HelloWorld:a(start=-0.5, *estimate*=-1.04807)
HelloWorld_cs_Fit.HelloWorld:x_start(start=0.5, *estimate*=1)

=====
0      convergence
HelloWorld.a startvalue=-0.5, estimatedvalue=-1.0480741793778
HelloWorld.x_start startvalue=0.5, estimatedvalue=0.99999999999972
HelloWorld.a estimation is OK: true
HelloWorld.x_start estimation is OK: true
info:    Logging information has been saved to "HelloWorld_cs_Fit.log"

```

## 6.2 Lua Scripting Commands

### 6.2.1 omsi\_initialize

This function initializes a given composite model. After this call, the model is in simulation mode.

```
-- simodel      [inout] SysIdent model as opaque pointer.
-- nSeries       [in] Number of measurement series.
-- time          [in] Array of measurement/input time instants.
-- inputvars     [in] Array of names of input variables (empty array if
↪none).
-- measurementvars [in] Array of names of observed measurement variables.
-- status         [out] Error status.
status = omsi_initialize(simodel, nSeries, time, inputvars,
↪measurementvars)
```

### 6.2.2 omsi\_addMeasurement

Add measurement values for a fitting variable.

```
-- simodel [inout] SysIdent model as opaque pointer.
-- iSeries  [in] Index of measurement series.
-- var     [in] Name of variable.
-- values   [in] Array of measured values for respective time instants.
```

(continues on next page)

(continued from previous page)

```
-- status [out] Error status.
status = omsi_addMeasurement(simodel, iSeries, var, values)
```

### 6.2.3 omsi\_addInput

Add input values for external model inputs.

If there are several measurement series, all series need to be conducted with the same external inputs!

```
-- simodel [inout] SysIdent model as opaque pointer.
-- var      [in] Name of input variable.
-- time     [in] Array of input time instants.
-- values   [in] Array of input values corresponding to respective "time" ↴
array entries in omsi_initialize().
-- status   [out] Error status.
status = omsi_addInput(simodel, var, time, values)
```

### 6.2.4 omsi\_newSysIdentModel

Creates an empty model for parameter estimation.

```
-- ident   [in] Name of the model instance as string.
-- simodel [out] SysIdent model instance as opaque pointer.
simodel = omsi_newSysIdentModel(ident)
```

### 6.2.5 omsi\_describe

Print summary of SysIdent model.

```
-- simodel [inout] SysIdent model as opaque pointer.
-- status   [out] Error status.
status = omsi_describe(simodel)
```

### 6.2.6 omsi\_getParameter

Get parameter that should be estimated.

```
-- simodel      [inout] SysIdent model as opaque pointer.
-- var          [in] Name of parameter.
-- startvalue   [out] Start value of parameter.
-- estimatedvalue [out] Estimated value of parameter.
-- status        [out] Error status.
status, startvalue, estimatedvalue = omsi_getParameter(simodel, var)
```

### 6.2.7 omsi\_addParameter

Add parameter that should be estimated.

```
-- simodel      [inout] SysIdent model as opaque pointer.
-- var          [in] Name of parameter.
-- startvalue   [in] Start value of parameter.
-- status       [out] Error status.
status = omsi_addParameter(simodel, var, startvalue)
```

## 6.2.8 omsi\_setOptions\_max\_num\_iterations

Set Ceres solver option *Solver::Options::max\_num\_iterations*.

```
-- simodel          [inout] SysIdent model as opaque pointer.
-- max_num_iterations [in] Maximum number of iterations for which the
--                      ↴solver
--                      should run (default: 25).
-- status           [out] Error status.
status = omsi_setOptions_max_num_iterations(simodel, max_num_iterations)
```

## 6.2.9 omsi\_solve

Solve parameter estimation problem.

```
-- simodel      [inout] SysIdent model as opaque pointer.
-- reporttype   [in] Print report and progress information after call to
--                      ↴Ceres solver.
--                      Supported report types: { "", "BriefReport", "FullReport
--                      ↴"}, where "" denotes no output.
-- status        [out] Error status.
status = omsi_solve(simodel, reporttype)
```

## 6.2.10 omsi\_getState

Get state of SysIdent model object.

```
-- simodel [inout] SysIdent model as opaque pointer.
-- state   [out] State of SysIdent model.
-- status   [out] Error status.
status, state = omsi_getState(simodel)
```

## 6.2.11 omsi\_freeSysIdentModel

Unloads a model.

```
-- simodel [inout] SysIdent model as opaque pointer.
omsi_freeSysIdentModel(simodel)
```



## SSP SUPPORT

Composite models are imported and exported in the *System Structure Description (SSD)* format, which is part of the *System Structure and Parameterization (SSP)* standard.

### 7.1 Bus Connections

Bus connections are saved as annotations to the SSD file. Bus connectors are only allowed in weakly coupled and strongly coupled systems. Bus connections can exist in any system type. Bus connectors are used to hide SSD connectors and bus connections are used to hide existing SSD connections in the graphical user interface. It is not required that all connectors referenced in a bus are connected. One bus may be connected to multiple other buses, and also to SSD connectors.

The example below contains a root system with two subsystems, WC1 and WC2. Bus connector WC1.bus1 is connected to WC2.bus2. Bus connector WC2.bus2 is also connected to SSD connector WC1.C3.

```
<?xml version="1.0" encoding="UTF-8"?>
<ssd:SystemStructureDescription name="Test" version="Draft20180219">
  <ssd:System name="Root">
    <ssd:Elements>
      <ssd:System name="WC2">
        <ssd:Connectors>
          <ssd:Connector name="C1" kind="input" type="Real"/>
          <ssd:Connector name="C2" kind="output" type="Real"/>
        </ssd:Connectors>
        <ssd:Annotations>
          <ssc:Annotation type="org.openmodelica">
            <oms:Bus name="bus2">
              <oms:Signals>
                <oms:Signal name="C1"/>
                <oms:Signal name="C2"/>
              </oms:Signals>
            </oms:Bus>
          </ssc:Annotation>
        </ssd:Annotations>
      </ssd:System>
      <ssd:System name="WC1">
        <ssd:Connectors>
          <ssd:Connector name="C1" kind="output" type="Real"/>
          <ssd:Connector name="C2" kind="input" type="Real"/>
          <ssd:Connector name="C3" kind="input" type="Real"/>
        </ssd:Connectors>
      </ssd:System>
    </ssd:Elements>
  </ssd:System>
</ssd:SystemStructureDescription>
```

(continues on next page)

(continued from previous page)

```

<ssd:Annotations>
  <ssc:Annotation type="org.openmodelica">
    <oms:Bus name="bus1">
      <oms:Signals>
        <oms:Signal name="C1"/>
        <oms:Signal name="C2"/>
      </oms:Signals>
    </oms:Bus>
  </ssc:Annotation>
</ssd:Annotations>
</ssd:System>
</ssd:Elements>
<ssd:Connections>
  <ssd:Connection startElement="WC2" startConnector="C1"
    endElement="WC1" endConnector="C1"/>
  <ssd:Connection startElement="WC2" startConnector="C2"
    endElement="WC1" endConnector="C2"/>
  <ssd:Connection startElement="WC2" startConnector="C2"
    endElement="WC1" endConnector="C3"/>
</ssd:Connections>
<ssd:Annotations>
  <ssc:Annotation type="org.openmodelica">
    <oms:Connections>
      <oms:Connection startElement="WC1" startConnector="bus1"
        endElement="WC2" endConnector="bus2"/>
      <oms:Connection startElement="WC2" startConnector="bus2"
        endElement="WC1" endConnector="C3"/>
    </oms:Connections>
  </ssc:Annotation>
</ssd:Annotations>
</ssd:System>
</ssd:SystemStructureDescription>

```

## 7.2 TLM Systems

TLM systems are only allowed on top-level. SSD annotations are used to specify the system type inside the ssd:SimulationInformation tag, as shown in the example below. Attributes ip, managerport and monitorport defines the socket communication, used both to exchange data with external tools and with internal simulation threads.

```

<?xml version="1.0"?>
<ssd:System name="tlm">
  <ssd:SimulationInformation>
    <ssd:Annotations>
      <ssd:Annotation type="org.openmodelica">
        <oms:TlmMaster ip="127.0.1.1" managerport="11111" monitorport=
        ↵"11121"/>
      </ssd:Annotation>
    </ssd:Annotations>
  </ssd:SimulationInformation>
  <ssd:Elements>
    <ssd:System name="weaklycoupled">
      <ssd:SimulationInformation>

```

(continues on next page)

(continued from previous page)

```

<ssd:FixedStepMaster description="oms-ma" stepSize="1e-1" />
</ssd:SimulationInformation>
</ssd:System>
</ssd:Elements>
</ssd:System>

```

## 7.3 TLM Connections

TLM connections are implemented without regular SSD connections. TLM connections are only allowed in TLM systems. TLM connectors are only allowed in weakly coupled or strongly coupled systems. Both connectors and connections are implemented as SSD annotations in the System tag.

The example below shows a TLM system containing two weakly coupled systems, wc1 and wc2. System wc1 contains two TLM connectors, one of type 1D signal and one of type 1D mechanical. System wc2 contains only a 1D signal type connector. The two 1D signal connectors are connected to each other in the TLM top-level system.

```

<?xml version="1.0"?>
<ssd:System name="tlm">
  <ssd:Elements>
    <ssd:System name="wc2">
      <ssd:Connectors>
        <ssd:Connector name="y" kind="input" type="Real" />
      </ssd:Connectors>
      <ssd:Annotations>
        <ssd:Annotation type="org.openmodelica">
          <oms:Bus name="bus2" type="tlm" domain="signal"
                    dimension="1" interpolation="none">
            <oms:Signals>
              <oms:Signal name="y" tlmType="value" />
            </oms:Signals>
          </oms:Bus>
        </ssd:Annotation>
      </ssd:Annotations>
    </ssd:System>
    <ssd:System name="wc1">
      <ssd:Connectors>
        <ssd:Connector name="y" kind="output" type="Real" />
        <ssd:Connector name="x" kind="output" type="Real" />
        <ssd:Connector name="v" kind="output" type="Real" />
        <ssd:Connector name="f" kind="input" type="Real" />
      </ssd:Connectors>
      <ssd:Annotations>
        <ssd:Annotation type="org.openmodelica">
          <oms:Bus name="bus1" type="tlm" domain="signal"
                    dimension="1" interpolation="none">
            <oms:Signals>
              <oms:Signal name="y" tlmType="value" />
            </oms:Signals>
          </oms:Bus>
          <oms:Bus name="bus2" type="tlm" domain="mechanical"
                    dimension="1" interpolation="none">
            <oms:Signals>

```

(continues on next page)

(continued from previous page)

```

<oms:Signal name="x" tlmType="state" />
<oms:Signal name="v" tlmType="flow" />
<oms:Signal name="f" tlmType="effort" />
</oms:Signals>
</oms:Bus>
</ssd:Annotation>
</ssd:Annotations>
</ssd:System>
</ssd:Elements>
</ssd:Annotations>
<ssd:Annotation type="org.openmodelica">
<oms:Connections>
<oms:Connection startElement="wcl" startConnector="bus1"
endElement="wc2" endConnector="bus2"
delay="0.001000" alpha="0.300000"
linearimpedance="100.000000"
angularimpedance="0.000000" />
</oms:Connections>
</ssd:Annotation>
</ssd:Annotations>
</ssd:System>

```

Depending on the type of TLM bus connector (dimension, domain and interpolation), connectors need to be assigned to different tlm variable types. Below is the complete list of supported TLM bus types and their respective connectors.

### 1D signal

tlmType	causality
"value"	input/output

### 1D physical (no interpolation)

tlmType	causality
"state"	output
"flow"	output
"effort"	input

### 1D physical (coarse-grained interpolation)

tlmType	causality
"state"	output
"flow"	output
"wave"	input
"impedance"	input

### 1D physical (fine-grained interpolation)

tlmType	causality
"state"	output
"flow"	output
"wave1"	input
"wave2"	input
"wave3"	input
"wave4"	input
"wave5"	input
"wave6"	input
"wave7"	input
"wave8"	input
"wave9"	input
"wave10"	input
"time1"	input
"time2"	input
"time3"	input
"time4"	input
"time5"	input
"time6"	input
"time7"	input
"time8"	input
"time9"	input
"time10"	input
"impedance"	input

### 3D physical (no interpolation)

tlmType	causality
"state1"	output
"state2"	output
"state3"	output
"A11"	output
"A12"	output
"A13"	output
"A21"	output
"A22"	output
"A23"	output
"A31"	output
"A32"	output
"A33"	output
"flow1"	output
"flow2"	output
"flow3"	output
"flow4"	output
"flow5"	output
"flow6"	output
"effort1"	input
"effort2"	input
"effort3"	input
"effort4"	input
"effort5"	input
"effort6"	input

### 3D physical (coarse-grained interpolation)

tlmType	causality
"state1"	output
"state2"	output
"state3"	output
"A11"	output
"A12"	output
"A13"	output
"A21"	output
"A22"	output
"A23"	output
"A31"	output
"A32"	output
"A33"	output
"flow1"	output
"flow2"	output
"flow3"	output
"flow4"	output
"flow5"	output
"flow6"	output
"wave1"	input
"wave2"	input
"wave3"	input
"wave4"	input
"wave5"	input
"wave6"	input
"linearimpedance"	input
"angularimpedance"	input

### 3D physical (fine-grained interpolation)

tlmType	causality
"state1"	output
"state2"	output
"state3"	output
"A11"	output
"A12"	output
"A13"	output
"A21"	output
"A22"	output
"A23"	output
"A31"	output
"A32"	output
"A33"	output
"flow1"	output
"flow2"	output
"flow3"	output
"flow4"	output
"flow5"	output

Continued on next page

Table 1 – continued from previous page

tlmType	causality
"f1ow6"	output
"wave1_1"	input
"wave1_2"	input
"wave1_3"	input
"wave1_4"	input
"wave1_5"	input
"wave1_6"	input
"wave2_1"	input
"wave2_2"	input
"wave2_3"	input
"wave2_4"	input
"wave2_5"	input
"wave2_6"	input
"wave3_1"	input
"wave3_2"	input
"wave3_3"	input
"wave3_4"	input
"wave3_5"	input
"wave3_6"	input
"wave4_1"	input
"wave4_2"	input
"wave4_3"	input
"wave4_4"	input
"wave4_5"	input
"wave4_6"	input
"wave5_1"	input
"wave5_2"	input
"wave5_3"	input
"wave5_4"	input
"wave5_5"	input
"wave5_6"	input
"wave6_1"	input
"wave6_2"	input
"wave6_3"	input
"wave6_4"	input
"wave6_5"	input
"wave6_6"	input
"wave7_1"	input
"wave7_2"	input
"wave7_3"	input
"wave7_4"	input
"wave7_5"	input
"wave7_6"	input
"wave8_1"	input
"wave8_2"	input
"wave8_3"	input
"wave8_4"	input

Continued on next page

Table 1 – continued from previous page

tlmType	causality
"wave8_5"	input
"wave8_6"	input
"wave9_1"	input
"wave9_2"	input
"wave9_3"	input
"wave9_4"	input
"wave9_5"	input
"wave9_6"	input
"wave10_1"	input
"wave10_2"	input
"wave10_3"	input
"wave10_4"	input
"wave10_5"	input
"wave10_6"	input
"time1"	input
"time2"	input
"time3"	input
"time4"	input
"time5"	input
"time6"	input
"time7"	input
"time8"	input
"time9"	input
"time10"	input
"linearimpedance"	input
"angularimpedance"	input



## INDEX

### O

OMSimulator, 1  
    Examples, 3  
    Flags, 3  
OMSimulatorLib, 4  
    C-API, 5  
OMSimulatorLua, 19  
    Examples, 21  
    Scripting Commands, 21  
OMSimulatorPython, 35  
    Examples, 37  
    Scripting Commands, 37  
OMSysIdent, 50  
    Examples, 51  
    Scripting Commands, 53

### S

SSP, 55  
    Bus connections, 57  
    TLM connections, 59  
    TLM Systems, 58